



## HYPLOT Multi: Saving File Enabled Status


By Joseph Adamski

A request we kept hearing when HYPLOT Multi was released was to add the ability to save the enabled / disabled status of the various files for each PLT (plotting) sheet. For example, you may want to show side scan data in one sheet, while displaying magnetometer data in another. In order to facilitate this, the HYPACK® PLT file format has been extended to store that information.

To avoid disrupting our users who prefer the method used in the past (where file display is synchronized in all PLT files), this feature is disabled by default. You must enable it for the PLT files you wish to have exhibit this behavior. The checkbox labeled “Save Order of Background Charts” in the Plotting Sheets tab is what controls whether the PLT will remember which files are enabled or disabled.

**To enable this feature**, check the Plotting Sheet Tab in the Control Panel.

*FIGURE 1. Option to Save Chart Order*



The next time you reload HYPLOT-Multi, the settings will be saved for the Data Files and Projects Files for the individual PLT.

**(Editor’s Note:** After further discussion, the label for this feature is likely to change. It will continue to work as described here.)